WxflowToChords README

This project provides a Python application for capturing the UDP packets that are emitted by a WeatherFlow Sky/Air or Tempest system hub, and transferring the data to a CHORDS data server.

Quickstart

Note that the CHORDS system administrator must enable measurements, data downloading, and data viewing for the registered CHORDS user.

Create a *WxflowToChords/wx.json* configuration file. Templates are provided for Tempest and Air/Sky WeatherFlow systems.

Set the following items in the configuration file:

System Type	Identifier	Value
Both	"chords_host"	The IP name of the CHORDS server.
Both	"api_email"	The user login email for the CHORDS portal.
Both	"api_key"	The user api_key for the CHORDS portal.
Both	HubStatus "serial_number"	change "HB_xxxxxxxxx" to the correct Hub serial number.
Both	"_chords_inst_id"	The CHORDS instrument id for your WeatherFlow device. There will be multiple occurances of this identifier.
Tempest	ObsTempest "serial_number"	change "ST_xxxxxxxxx" to the correct Tempest serial number. There will be multiple occurances of this identifier.
Air/Sky	ObsSky "serial_number"	change "SK_xxxxxxxx" to the correct Sky serial number. There will be multiple occurances of this identifier.
AirSky	ObsTempest "serial_number"	change "AR_xxxxxxxx" to the correct Air serial number.

Run WxflowToChords. The configuration file name is the single parameter:

python3 WxflowToChords wx.json

Of course, when you log off, the process will stop, so you may wish to run it it as:

nohup python3 WxflowToChords wx.json &

Any time the system is rebooted, you will need to restart WxflowToChords. You can get around this by setting up and enabling a service approprate for your operating system. A sample systemd service definition file is provided here.

About

(See Raspbian Installation below for installation instructions on an RPi).

WxflowToChords are a set of python modules for converting Weatherflow json formatted datagrams into the CHORDS REST api, and submitting the data to a CHORDS portal.

There are four python modules:

- FromWxflow: Capture datagrams and put them in a queue. This is multithreaded, so that datagram reading can occur in parallel with other processing.
- DecodeWxflow: Translate the wxflow messages into structured data matching the CHORDS REST api. A
 JSON based configuration specifies the translation.
- ToChords: Send the structured data to a CHORDS portal. This is multithreaded, so that http writing can
 occur in parallel with other processing. The same JSON configuration provides other information for the
 CHORDS connection.
- WxflowToChords: Strings all three modules together for the end-to-end process.

Each module expects a configuration, provided in a JSON file. A single file can contain the configuration for all modules, or a file can be created for just the items needed for a gven module.

Each module will run a test case if it is invoked individually.

This code will be run on both regular computers, and systems such as the Raspberry Pi Zero W. The code has been tested against python3 on MacOS and Raspbian Bullseye Lite.

Weatherflow JSON Schema

Input data is structured according to the Weatherflow UDP JSON schema. Messages have atype field identifying the type of message, status fields indicating identity and hardware health, and in some cases an obs array containing the observed values, in a predefined order.

Unfortunately, the meaning of each obs array element is not identified in the message; you have to refer to the documentation to determine this. Other values, such as voltage and rssi, can be located by identifier.

For example:

```
{
    "serial_number":"HB-00000001",
    "type":"hub_status",
    "firmware_revision":"13",
    "uptime":1670133,
    "rssi":-62,
    "timestamp":1495724691,
    "reset_flags": 234881026,
    "stack": "1616,1608"
}
```

```
{
    "serial_number": "SK-00008453",
    "type":"rapid_wind",
    "device_id":1110,
    "hub_sn": "HB-00000001",
    "obs":[1493322445,2.3,128]
}
```

```
{
    "serial_number": "AR-00004049",
    "type": "device_status",
    "hub_sn": "HB-00000001",
    "timestamp": 1510855923,
    "uptime": 2189,
    "voltage": 3.50,
    "firmware_revision": 17,
    "rssi": -17,
    "sensor_status": 0
}
```

The WeatherFlow documentation seems to be in flux, so be sure to capture some datagrams to verify what they are transmitting.

FromWxflow

This module captures the broadcast datagrams from the weather station hub. It requires a JSON configuration file containing:

```
{
    "listen_port": 5022
}
```

DecodeWxflow

A JSON structure defines the mapping between the wxflow input data and the CHORDS portal api. A collection of wxflow decoders are defined (wxflow_decoders), for each message that is to be translated. Each one contains a list of match attributes. If an incoming messages matches one of the wxflow_decoders, that entry is used to decode the message.

The wxflow_type in wxflow_decoders (e.g. "ObsAir") are user-assigned, and have no special meaning.

Within each message decoding specification, there are two types of keys. If one begins with an underscore, it is a directive to the decoder, such as <u>_enabled</u> or <u>_match</u>. Otherwise, it is a key that will match a field in the incoming message, and the element directs further message handling.

The obs element has special meaning. It contains instructions on how to route the elements of an wxflow obs array.

If a CHORDS variable is identified as at, it will be converted to a timestamp and used for the at= timestamp.

```
{
  "chords_host": "chords_host.com",
  "listen_port": 50222,
  "api_email": "my_chords_registered_email@gmail.com",
  "api_key": "inscrutableapikey",
  "wxflow_decoders": [
    {
        "_enabled": true,
        "_wxflow_type": "ObsAir",
        "_chords_inst_id": "1",
        "_match": {
```

```
"type": "obs_air",
         "serial_number": "AR-00005436"
       },
       "obs":[
           s":[
  [0, "at"],
  [1, "pres"],
  [2, "tdry"],
  [3, "rh"],
  [4, "lcount"],
  [5, "ldist"],
  [6, "vbat"]
       "_enabled": true,
       "_wxflow_type": "HubStatus",
       "_chords_inst_id": "1",
       __match": {
        "type": "hub_status",
         "serial_number": "HB-00004236"
       "timestamp": {
         "chords_var": "at"
       "rssi" :{
         "chords_var": "rssihub"
      "_enabled": true,
       "_wxflow_type": "StationStatus",
       "_chords_inst_id": "1",
       "_match": {
   "type": "station_status",
         "serial_number": "AR-00005436"
       "timestamp": {
         "chords_var": "at"
       "voltage": {
           "chords_var": "vair"
       "rssi": {
         "chords_var": "rssiair"
       "sensor_status": {
         "chords_var": "statair"
    }
 ]
}
```

ToChords

This module takes the CHORDS data structure, reformats it as a URL, and sents it to a CHORDS instance as an http GET. There are two steps in this process, to bulid the URL and then submit it for transmission. This can be seen in WxflowToChords:

```
uri = ToChords.buildURI(host, chords_record)
ToChords.submitURI(uri)
```

ToChords requires a JSON configuration file containing the host name for the CHORDS instance, and the access key that is included in the GET.

```
{
    "chords_host": "chords_host.com",
    "skey": "key"
}
```

WxflowToChords

This module strings the three preceding ones together. It's the best place to see how the modules work.

Example processing, showing the wxflow datagram followed by the CHORDS structured data:

```
{"serial number":"HB-
00004236", "type": "hub_status", "firmware_version": "26", "uptime": 88638, "rssi": -58, "timestamp": 151145614
8, "reset_flags": 503316482}
{
 "inst_id": "1"
 "skey": "123456",
 "vars": {
   "at": 1511456148,
   "rssihub": -58
 }
{"serial number": "AR-00005436", "type": "station status", "hub sn": "HB-
00004236", "timestamp": 1511456154, "uptime": 1825691, "voltage": 3.46, "version": 20, "rssi": -73, "sensor_stat
us":4}
{
 "inst_id": "1"
 "skey": "123456",
 "vars": {
   "at": 1511456154,
   "rssiair": -73,
   "statair": 4,
   "vair": 3.46
 }
}
{"serial_number":"AR-00005436","type":"obs_air","hub_sn":"HB-00004236","obs":
[[1511456154,770.00,13.43,33,0,0,3.46,1]],"firmware_revision":20}
 "inst id": "1"
 "skey": "123456",
 "vars": {
   "at": 1511456154,
   "lcount": 0,
    "ldist": 0,
   "pres": 770.0,
   "rh": 33,
   "tdry": 13.43,
   "vbat": 3.46
}
```

Raspbian Installation

This method is used to install Raspbian on a headless Raspberry Pi Zero W.

- 1. Get and run the latest RPi imager release download from GitHub: https://github.com/raspberrypi/rpi-imager
- 2. Hit shift-cmd-x to enable headless setup.
- 3. Use the settings menu to set:
 - Wifi

- Ssh enabled (via password)
- Hostname (e.g. wxflow)
- 4. Select raspbian 32 bit lite (for arm6/arm7 systems).
- 5. Write!
- 6. Boot up
- 7. ssh in, pull WxflowToChords, and configure as described above.

Micropython Notes (Deprecated)

I tried to get this working on a WiPy. It would run for indeterminate periods, and then throw OSError exceptions in the urequests code. After this, the networking would not work until after a reboot. So, I ripped out the WiPy specifics, and transfered the project to a Raspberry Pi Zero W. Here are a few thoings learned while working with the WiPy.

General

Micropython is a slimmed down embedded version of python. The Ur-project seems to be micropython.org, but i have learned that many device developers (pycom, adafruit, microbit) have forked this project, and incompatibilities may exist. It seems that most of the customizations are related to the particular hardware set, but that doesn't mean that they will track the micropython.org releases.

On macOS

The goal is to have this running on a micropython embedded system. Fortunately, there is a micropython implmentation for Linux, macOS and Windows. This has been useful for testing the code apart from the embedded hardware. However, my experieince has been that the macOS version is not bug-for-bug identical to the micropython board that I have been using (the WiPy, and so this will only get you soo far.

The general idea for bringing up micropython on macOS:

```
brew install libffi
git clone --recurse https://github.com/micropython/micropython.git
cd micropython/ports/unix
make axtls
PKG_CONFIG_PATH=/usr/local/opt/libffi/lib/pkgconfig make install
./micropython
>>> import upip
>>> upip.install('micropython-socket')
>>> upip.install('micropython-json')
>>> upip.install('micropython-thread')
>>> upip.install('micropython-os')
```